
Windows: Outlook 2013 (IMAP)

This article will assist you with setting up Outlook 2013 with your Hosted Mailbox.

- 1. Click on the Start Menu (or press the Windows key) and then search for Control Panel
- 2. Once in the Control Panel, Click on Mail
- 3. When the Mail Control Panel opens, select Show Profiles



4. Select Add to add a new profile. Enter any name you wish and select OK

🥬 Mail			
General			
The follo	owing profile	es are set up on	this computer:
			^
			~
Add	Remove	Properties	Copy
-		utlook, use this	s profile:
_	or a profile t ise this profil		
	ise this profil	e	
			~



5. Select Manual setup or additional server types. Click Next

۹	Add Account	×
Auto Account Setup Manual setup of an	account or connect to other server types.	×
) E-mail <u>A</u> ccount		
Your Name:	Example: Ellen Adams	
<u>E</u> -mail Address:	Example: ellen@contoso.com	
Password: Retype Password:		
	Type the password your Internet service provider has given you.	
<u>Manual setup or ad</u>		
	< <u>B</u> ack <u>N</u> ext >	Cancel

6. Select **POP or IMAP** and click **Next**

Add Account			
Choose Service			×
O Microsoft Exchange Server or compatible service			
Connect to an Exchange account to access email, calendars, co	ntacts, tasks, and	voice mail	
 Outlook.com or Exchange ActiveSync compatible service Connect to a service such as Outlook.com to access email, caler 	ndars contacts an	d tasks	
POP or IMAP			
Connect to a POP or IMAP email account			
		2	
	< Back	Next >	Cancel

7. In the Add New Account window, input the following information:

Email Address: <your email> Account Type: IMAP Incoming Mail Server: secure.emailsrvr.com Outgoing Mail Server: secure.emailsrvr.com

User Name: <your email> Password: Your mailbox password

- 8. Click on More Settings then click the Outgoing Server Tab
- 9. Check the box for **My outgoing server (SMTP) requires authentication** Check the button for **Use same settings as my incoming mail server**

Internet E-mail Settin	gs	\times
General Outgoing	Server Advanced	
My outgoing sen	ver (SMTP) requires authentication	
Use same sett	tings as my incoming mail server	
O Log on using		
User Name:		
Password:		
	Remember password	
Require S	ecure Password Authentication (SPA)	
	OK	Cancel

10. Change **Use the following type of encrypted connection** to **SSL** Change the port numbers to match the image below.

Internet E-mail Settings

General Outgoing Server Advanced
Server Port Numbers
Incoming server (IMAP): 993 Use Defaults
Use the following type of encrypted connection: SSL
Outgoing server (SMTP): 465
Use the following type of encrypted connection: SSL
Server Timeouts
Short Long 1 minute
Folders
Root folder path:
Sent Items
Do not save copies of sent items
Deleted Items
Mark items for deletion but do not move them automatically
Items marked for deletion will be permanently deleted when the items in the mailbox are purged.
Purge items when switching folders while online
OK Cancel

- 11. Click OK
- 12. Click **Next**. Outlook will now attempt to send a test message using the settings we have just put in. If everything was entered correctly, the message will send out successfully.

 \times

Test Acc	count Settings		
Congrate continue	ulations! All tests completed successfully	. Click Close to	Stop Close
Tasks	Errors		
	g onto incoming mail server (IMAP) nd test e-mail message	Status Completed Completed	

13. **Congratulations!** You have now setup Outlook to work with your Mailbox. Please wait 15 minutes before troubleshooting to allow for mail to download.